


Add features to and remove features from an offline image with DISM

example, to see the images within an image file named Install.wim that is stored in C:\images, type the following:

```
Dism /Get-ImageInfo /ImageFile:C:\images\install.wim
```



```
Administrator: Windows PowerShell
PS C:\Users\Administrator> Dism /Get-ImageInfo /ImageFile:c:\images\install.wim

Deployment Image Servicing and Management tool
Version: 6.2.8400.0

Details for image : c:\images\install.wim

Index : 1
Name : Windows Server 8 Beta SERVERSTANDARDCORE
Description : Windows Server 8 Beta SERVERSTANDARDCORE
Size : 7,054,646,034 bytes

Index : 2
Name : Windows Server 8 Beta SERVERSTANDARD
Description : Windows Server 8 Beta SERVERSTANDARD
Size : 11,849,571,677 bytes

Index : 3
Name : Windows Server 8 Beta SERVERDATACENTERCORE
Description : Windows Server 8 Beta SERVERDATACENTERCORE
Size : 7,050,514,952 bytes

Index : 4
Name : Windows Server 8 Beta SERVERDATACENTER
Description : Windows Server 8 Beta SERVERDATACENTER
Size : 11,854,358,781 bytes

The operation completed successfully.
```

Once you know the name or index of the desired image, you can mount it in a specified directory. For example, use the following command to mount the image with index 2 in the C:\images\offline directory:

```
Dism /Mount-Image /ImageFile:C:\images\install.wim /index:2 /MountDir:C:\images\offline
```

Finally, you can use DISM to point to the mounted image and enable a desired feature. You can use the /All argument to enable all the parent features in the same command. For example, to enable the Remote-Desktop-Services role and all parent features, type the following:

```
Dism /Image:C:\images\offline /Enable-Feature /FeatureName:Remote-Desktop-Services /All
```

If you want to remove a feature from or disable a feature on an offline image, use the /Disable-Feature switch. For example:

```
Dism /Image:C:\images\offline /Disable-Feature /FeatureName:Remote-Desktop-Services
```

